



1. Unpack the file to local: wfm_to_csv_tool.rar
2. Run the EXE program: wfm_to_csv.exe. You will see the following software interface.




3. Select the *.wfm file path.



4. Select the an analog channel to obtain data. The length is automatically set to the total number of waveform points in the channel.




5. Configure whether the CSV file contains sequence and time information.



6. Click the button 'Convert to CSV'. You can choose the csv file path and make

name for the file. Then you will get the csv file and the plotted waveform. If you don't want to display the waveform, you can select the 'No display'.



Convert to CSV

☐ No Display